Mobile CMS

Mobile CMS

User's Manual



V2.08-o129 This document contains preliminary information and is subject to change without notice.

14.1 Requirements

• OS

higher version.

- Memory
- : 512Kb or Higher. : Smartphone
- Device : Smartphone
 Network : Available all wireless networking method. I.e. Wi-fi, HSDPA, Wibro.

:

Windows Mobile 6.1 or

14.2 Installation

- Prepare ActiveSync program to user's PC.
 - Available download at following link.
 - http://www.microsoft.com/downloads/details.aspx?FamilyID=9e641c34-6f7f-404d-a04b-dc09f8141141&DisplayLang=en
 - ActiveSync enable users manage documents, calendars, contact lists and email between their PC and mobile device through a Cradle or a USB connection.
- Connect mobile device to PC then double click "Setup_MobileCOM.exe" to start installation.
- The following screen will appear:

IobileCMS
Pocket PC installation MobileCMS will be installed on your Pocket PC now
USE: Smartphone : WinCE 6.0 / WinCE 6.1
< Back Next > Cancel

• Click "Next" button.

MobileCMS			×	
License Agreement				
Please read the following license agreem	ient carefully.			
MahiaCMC arearan				
			Ţ	
I accept the terms in the license agreement				
C I do not accept the terms in the license agreement				
	< Back	Finish	Cancel	

• Click accepting the license agreement, then click "Finish" button.

Select remove	a program's check box if you want to install it on yo e the program from your device.	ur mobile device, or clear the	check box if you want to
lote:	If a program that you installed is not listed, the prog	am was not designed to be u	sed on your mobile device.
	Application Downloading Complete		X
	Please check your mobile device screen to complete this installation.	see if additional steps are	necessary to
Prog			ОК
Prog Space Space	e required for selected programs: e available on device:	Ş	ОК

- Installation box will appear
- Click [OK] to start installation.
- When installation completed, following pop-up will appear.
- Click [OK].
- If following message appeared, it has successfully installed.



(Note)

Depending on mobile device, successful installation message may not appear. Click [OK] when license agreement message appear.

• Move to [Programs] page to check whether CMS has installed.

😚 Settings 🛛 🗹 🗮	t 7 _× 4€ 0	ok
Remove Programs		
Programs in storage memory:		
. MobileCMS		
	Remove	
Total storage memory available:	27842	<

14.3 Site configuration

• Start CMS, following screen will appear.



Add

• Click [Add] to appear following screen.

월 mobiledlg	🗹 🗱 🎝 🕂 🔤
Site Name	IP Address/Domain Name
•	
Connect Ex	Add Edit Del
Ok	

- Fill in correct information.
 - Site Name : Insert the name of site. IP/Domain Insert the IP : _ address or Domain name of the site. ID

2

- Input the registered ID of the site. : Password Input the _ ÷
- password of the registered ID.
- Command Port Insert Command Port of the site. : _ Insert Stream Port of the site.
- _ Stream Port
- Click [Save] then following screen will appear with registered site.

👫 mobiledlg		S 🛱	Y_x 	ok
Site Name	IP Addr	ess/Do	main N	lame
office	19	2,168.	10.135	
•				•
Connect Ex	it	Add	Edit	Del
Ok				

Edit

• Select a site and click [Edit] then following screen will appear.

将 mobiledlg	⊠ # 7 _× 4€ ok			
Site Name	office			
IP/Domain	192.168.10.135			
ID	admin			
Password	****			
Command Port	5920			
Stream Port	5921			
Save Cancel				

• Correct items then click [Save].

Delete

• Select a site and click [Del].

• Confirmation message will pop up.

윩 mobiledlg	⊠ #* * x €
Site Name	IP Address/Domain Name
office	192.168.10.135
MobileCM	5
🕐 Ar	e you sure to delete?
Y	es No
•	III
Connect Ex	it Add Edit Del
Ok	

• Click [Yes] then the site information will be removed.

14.4 Connect

• Select a site then click [Connect].



- Live display screen of the site will appear if it is successfully connected.
 Users are able to select a camera by clicking camera button.
 Click [Disconnect] then, live display screen will be closed and Site list box will appear.

14.5 Uninstall

- Move to [Program Menu> System] then click [Remove Programs].
 The currently installed list will show up.

Settings 🛛 🗹 🖡	*	¶ _×	ok
Remove Programs			
Programs in storage memory:			
. MobileCMS			
	_		
l	ł	Remove	•
Total storage memory available:		2784	2К

• Choose Mobile CMS on the list and click [Remove].

😚 Settings 🛛 🗱 🏹 📢			
Remove Programs			
P Remove Program			
The selected program will be permanently removed. You may reload it from your desktop computer. Are you sure you want to remove it?			
Remove			
Total storage memory available: 27842K			

- Confirmation message will pop up
 Click [Yes] to complete uninstall then program will be removed.